# Installation and Operating Instructions Audit Trail Software for 6126/6127/6128/6129 Series

# **General Notes**

- These instructions are for installing S&G Audit Software (and all associated software components) and using it to capture, review, and save audit trail information from Sargent & Greenleaf 6126 and 6127 Audit Locks, and 6128 and 6129 Aseries Locks in Bank Mode.
- Software components to be installed include: .NET framework (required to run the SG Audit Software) Crystal Report drivers Touch Key drivers SG Audit Software
- oft-29 Tree Site Or W Tree Site Or W Site Or #
- The Audit software kit permits the tracking and documenting of lock usage by user, operation, time, and date. This information can be archived and/or exported in formats that allow it to be integrated with common computer applications for generating reports.
- This software will run on computers operating under Windows 7<sup>®</sup> and Windows XP Pro<sup>®</sup>.
- Transfer of the audit trail information from the lock to your computer is accomplished via Dallas iButton Touch Keys<sup>®</sup>. This eliminates the need for direct physical or electronic connection between the lock and the computer. Audit trails can be downloaded at the safe location, then sent anywhere in the world for uploading and analysis.
- Audit trail information is securely encoded when downloaded from the lock to the Dallas iButton Touch Key. It is then decoded when uploaded from the key to the computer running the Audit Software.

# **TABLE OF CONTENTS**

Software Installation (General)	02
Installing .NET Version 4.0	02
Installing Crystal Reports 13.0	04
Installing Touch Key Drivers	06
Installing the SG Audit Software	10
Software Operation (General)	13
Changing Logon Information	13
Adding and Deleting Managers	14
Audit Upload Window	15
Lock Registration	15
Modify a Lock	15
Delete a Lock	15
Add a Lock	15
About Lock Information Fields	15
Touch Key Preparation	16
Uploading and Saving the Audit Trail	17
Managing Audit Report Information	17
Software Version	18

#### Sargent & Greenleaf, Inc.

A Wholly Owned Subsidiary of Stanley Security Solutions, Inc. PO Box 930, Nicholasville, Kentucky 40340-0930 USA Phone (859) 885-9411 Phone (800) 826-7652 FAX (859) 887-2057 FAX (800) 634-4843



Sargent & Greenleaf S.A. 9, chemin du Croset 1024 Ecublens, Switzerland Phone +41-21 694 34 00 FAX +41-21 694 34 09

Copyright<sup>®</sup> 2012, Sargent & Greenleaf, Inc.

Document 630-845 Revised 2/20/2012

# Software Installation:

This section explains the process of installing the SG Audit Software and all of the required components. It includes the following components and detailed steps for installing each. <u>Install each software component in the order listed below</u>.

- .NET framework (required to run the SG Audit Software)
- Crystal Report drivers
- Touch key drivers
- SG Audit Software

# **Main Installation Screen**

When the SG Audit Software installation CD is inserted into your computer, the main installation screen should automatically be displayed. If this does not happen, navigate to the CD and run the **Autorun.exe** program.



Sargent & Greenleaf, Inc.

SG Audit Software

Install .Net Version 4.0

Install Crystal Reports 13.0

nstall Touchkey Drivers

A Program Installation

SARGENT AND GREENLEAF

SARGENT AND GREENLEAF and S&G, are trademarks of the Stanley Works or its affiliates

STANLEY, STANLEY in a notched rectangle

@ 2011 Sargent and Greenleaf

Windows 7 Vista Server 2008 Server 2003 SYXP

System

# **Selecting Your Operating System**

You should first select your operating system from the drop-down menu. The available operating systems include Windows XP, Windows 7, Windows Server 2003, Windows Server 2008 and Windows Vista.

After selecting your operating system, all of the necessary components for the software installation will be displayed (yellow buttons). The components should be installed in order from top to bottom. Simply click on the appropriate button to begin the installation routine. Following are detailed installation steps for each components.

- 1. Installing .NET Version 4.0
- 2. Installing Crystal Reports 13.0
- 3. Installing the iButton / Touch Key Drivers
- 4. Installing the SG Audit Software

# **Installing .NET Version 4.0**

The .NET framework contains a set of drivers required to run the SG Audit Software. The .NET framework is a standard Microsoft component that may already be installed on your system.

1. Start the installation routine for the SG Audit Software. This program should load automatically when the CD is inserted. If not, navigate to the CD and run the "Autorun.exe" program.



#### Installing .NET Version 4.0 (continued)

2. Click the **Install .Net Version 4.0** option. The files for the installation will be automatically extracted to your system.



3. The license information will be displayed first. If you agree with the license, select the **I have read and ACCEPT the terms of the License Agreement** option and click the **Install** button to continue. Note that if you do not agree to and accept the license agreement, this software will not be installed.

The progress of the installation will be displayed.



4. When the installation has been completed, a window will appear confirming the installation. Click the **Finish** button to close the installation routine.

This will complete the installation for the .NET Framework drivers. The SG Audit Software installation menu will be displayed again (shown at top of next page).

Please note that you may be asked to restart your system at this time. If you do restart your computer, then you will need to run the Autorun.exe program from the CD to display the installation menu.



# **Installing Crystal Reports 13.0**

The following steps outline the installation of the drivers required for Crystal Reports. This is the software that is used to generate the various reports within SG Audit Software.

1. Start the installation routine for the SG Audit Software. This program should load automatically when the CD is inserted. If not, navigate to the CD and run the **Autorun.exe** program.



- 2. Click the option to Install 🖀 Program Installation Crystal Reports 13.0. When you select this option Sargent & Greenleaf, Inc. from the menu, a new window SG Audit Software SARGENT AND GREENLEAF® will appear for the driver installation for Crystal Reports. STANLEY, STANLEY in a notched rectangle SARGENT AND GREENLEAF and S&G, are trademarks of the Stanley Works or its affiliates Simply click Next to continue. © 2011 Sargent and Greenleaf Install .Net Version 4.0 ~ Install Crystal Reports 13.0 BAP Crystal Reports ru ntime engine for .NET Framework 4 (32-... 🔳 🗖 🛽 Install Touchkey Drivers Install Program Welcome to the SAP Crystal Reports runtime engin for .NET Framework 4 (32-bit) Installation Wizard Type Software x86 (32 Bits) Exit It is strongly recommended that you exit all Windows programs before running this Setup Program. x64 (64 Bits) Click Cancel to quit Setup and close any programs you have running. Click Next to continue with the Setup program . RNING: This program is protected by copyright law and ernational treaties. Unauthorized reproduction or distribution of this program, or any portion of it, may result in severe civil and criminal penalties, and will be prosecuted to the maximum extent possible under law. < Back Next > Cancel
- 3. The license information will be displayed next. If you agree with the license, select the **I accept the License Agreement** option and click the **Next** button to continue. Please note that if you do not agree to and accept the license agreement, this software will not be installed.



#### Installing Crystal Reports 13.0 (continued)

 A new window will appear prompting if you are ready to begin the installation. Simply click **Next** to continue.

The installation will begin and the progress will be shown on the screen.



5. When the installation routine has completed, then a window will appear showing that the installation was successful. Click the **Finish** button to continue.

This completes the installation for the Crystal Reports drivers. The SG Audit Software installation menu will be displayed again (shown at top of next page).



## Installing the iButton / Touch Key Drivers

The following steps outline the installation for the touch key drivers. These drivers are required to allow communication with the touch keys and reader.

1. Start the installation routine for the SG Audit Software. This program should load automatically when the CD is inserted. If not, navigate to the CD and run the **Autorun.exe** program.



2. Click the option to **Install Touchkey Drivers**. The installation routine for the touch key drivers will begin. Click the **Next** button to continue



3. The license information will be displayed next. If you agree with the license, then select the I accept the terms in the License Agreement option and click the Next button to continue. Please note that if you do not agree to and accept the license agreement, then this software will not be installed.

1-Wire Drivers Version 4.03	Setup		
nd-User License Agreement Please read the following license ag	greement careful	ly ly	
Copyright (C) 2011 Max Rights Reserved.	xim Integr	ated Products,	A11 🔺
Permission is hereby of person obtaining a con- associated documentat. deal in the Software of without limitation the merge, publish, distr copies of the Softwar whom the Software is a	granted, f py of this ion files without re e rights t ibute, sub e, and to furnished	ree of charge, software and (the "Software" striction, incl o use, copy, mo license, and/or permit persons to do so, subje	to any '), to Luding odify, c sell to ect to
I accept the terms in the License	Agreement		
Print	Ba	ck <u>N</u> ext	Cancel

## Installing the iButton / Touch Key Drivers (continued)

4. The destination screen will be displayed next. Select the destination folder for the drivers and click the **Next** button. It is suggested to you simply accept the default values.

1-Wire Drivers Version 4.03 Setup	
Destination Folder Click Next to install to the default folder or click Change to choose another.	XIM
Install 1-Wire Drivers Version 4.03 to:	
C:\Program Files\Maxim Integrated Products\1-Wire Drivers x86\	
Change	
<u>B</u> ack Next	Cancel

5. A window will appear prompting you to disconnect all iButton readers from the computer before continuing. Please remove all adapters and then click the **Install** button to continue. The installation will begin and the status will be displayed on the screen.

🔀 1-Wire Drivers Version 4.03 Setup		
Unplug 1-Wire Adapters		
Before continuing, unplug all 1-Wire Adapters. Then, clic Click Back to review or change any of your installation se wizard.	k Install to begin the installation. ttings. Click Cancel to exit the	n.
		🔂 1-Wire Drivers Version 4.03 Setup
		Installing 1-Wire Drivers Version 4.03
		Please wait while the Setup Wizard installs 1-Wire Drivers Version 4.03.
		Status:
Back	Install Cancel	e
		7
		Back Next Cancel

6. After the installation has completed, click the **Finish** button to end the install routine.



### Installing the iButton / Touch Key Drivers (continued)

 After you close the touch key driver installation, a window will appear instructing you to define the touch key reader type and port. Click the OK button to continue.



8. Connect the touch key reader to your computer at this time. The computer should notice the new hardware and display the new hardware wizard.

Found New Hardware Wizard		
	Welcome to the Found New Hardware Wizard	
	This wizard helps you install software for:	
	USB Host Adapter for 1-Wire Network using WinUSB	
	If your hardware came with an installation CD or floppy disk, insert it now.	
	<ul> <li>Install the software automatically (Recommended)</li> <li>Install from a list or specific location (Advanced)</li> </ul>	
	Click Next to continue.	
	< Back Next > Cancel	

9. Select the option to **Install the software automatically** and click the **Next** button.



10. The computer will begin searching for the drivers and should automatically find the touch key drivers that were previously installed.

After the drivers have been found and installed, click the **Finish** button to complete the installation routine.



#### Installing the iButton / Touch Key Drivers (continued)

11. Verify that the reader can be detected by opening the **Auto Detect** routine. This is accomplished by selecting **START** followed by **PROGRAMS** followed by **1-WIRE DRIVERS X64** followed by **DEFAULT 1-WIRE NET**.

12. When the detection routine starts, click the **Auto Detect** button to begin the process.

13. A window should appear showing that the touch key reader was found. Click the **Yes** button to save the changes and continue. A window will appear showing that the sequence has been completed. Click the **OK** button to continue.



Lefault 1-Wire Network Settings

<u>File H</u>elp

Auto Detect

Auto Detect



14. The **Default 1-Wire Net** installation screen will be displayed again. Simply close this window to continue.

The touch key drivers should now be installed and ready to use with the SG Audit Software. The installation routine will return to the touch key message. Simply click the **OK** button to close the window and return to the main installation screen.

#### Installing the SG Audit Software

The SG Audit Software is the main software that is used to add locks and review the audit trail information. The following steps outline the installation of the SG Audit Software.

1. Start the installation routine for the SG Audit Software. This program should load automatically when the CD is inserted. If not, navigate to the CD and run the **Autorun.exe** program.

2. Click the option to Install Program.

3. When the installation begins, click the **Next** button to start the install routine

4. The license information will be displayed next. If you agree with the license, then select the **I accept the terms in the license agreement** option and click the **Next** button to continue. Please note that if you do not agree to and accept the license agreement, then this software will not be installed.

(continued on next page)

page 10

x64 (64 Bits)	
ogram Installation	
(SG	Sargent & Greenleaf, Inc.
STANLEY	SG Audit Software
SARGENT AND GRE	ENLEAF®
STANLEY, STANLEY in a notched	d rectangle
SARGENT AND GREENLEAF and	d S&G, are trademarks of the Stanley Works or its affiliates.
© 2011 Sargent and Greenleaf	
System	Install .Net Version 4.0
~	Install Crystal Reports 13.0
	Install Touchkey Drivers
Type Software	Install Program
• x86 (32 Bits)	Exit
x64 (64 Bits)	
_	
👸 SG Audit Software - In	stallShield Wizard
PAT	Welcome to the InstallShield Wizard for SG Audit Software
	The InstallShield(R) Wizard will install SG Audit Software on your computer. To continue, dick Next
	your computer i to continuely electricate
- ALL ALL	
	WARNING: This program is protected by copyright law and
a state	international treaties.
	< Back Next > Cancel
🛃 SG Audit Software - In	stallShield Wizard
i G Audit Software - In License Agreement	stallShield Wizard
<b>退 SG Audit Software - In</b> License Agreement Please read the following lic	stallShield Wizard
I SG Audit Software - In License Agreement Please read the following lice	InstallShield Wizard
SG Audit Software - In License Agreement Please read the following lic SOF	IstallShield Wizard
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL	InstallShield Wizard cense agreement carefully. <u>TWARE LICENSE AGREEMENT</u> D THIS DOCUMENT CAREFULLY
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE READ This Software License AG	And A set and A
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE READ This Software License Ag the date on which the So (the "Effective Date") betw	InstallShield Wizard cense agreement carefully. TWARE LICENSE AGREEMENT D THIS DOCUMENT CAREFULLY prevented in the state of the Purchase Order tware is installed or the date of the Purchase Order vers Sargent & Greenleaf, Inc ("S&G") and the party
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL This Software License Ag the date on which the So (the ' <u>Effective Date</u> ') betw identified on the Purchase	InstallShield Wizard cense agreement carefully. TWARE LICENSE AGREEMENT D THIS DOCUMENT CAREFULLY greement ( <u>"Agreement</u> ") is effective as of the earlier of fiware is installed or the date of the Purchase Order veen Sargent & Greenleaf, Inc ( <u>"S&amp;G</u> ") and the party e Order ( <u>"Licensee"</u> ).
Image: Solution         Solution           License Agreement         Please read the following lice           Please read the following lice         SOE           PLEASE REAL         This Software License Agree on which the Sol (the 'Effective Date') between identified on the Purchase	InstallShield Wizard cense agreement carefully. TWARE LICENSE AGREEMENT D THIS DOCUMENT CAREFULLY greement ( <u>"Agreement"</u> ) is effective as of the earlier of fiware is installed or the date of the Purchase Order veen Sargent & Greenleaf. Inc ( <u>"S&amp;G"</u> ) and the party e Order ( <u>Licensee</u> ). BACKGROUND
Image: Solution         Solution           License Agreement         Please read the following lice           Please read the following lice         SOE           PLEASE REAL         This Software License Agree on which the Sol (the 'Effective Date') between identified on the Purchase           Image: Agreement of the terms in the lice         Image: Agreement of the terms in the lice	InstallShield Wizard cense agreement carefuly. TWARE LICENSE AGREEMENT D THIS DOCUMENT CAREFULLY greement ( <u>'Agreement</u> ) is effective as of the earlier of fiware is installed or the date of the Purchase Order veen Sargent & Greenleaf, Inc ( <u>'S&amp;G</u> ') and the party e Order ( <u>'Licensee</u> '). BACKGROUND we nese agreement
SG Audit. Software - In           License Agreement           Please read the following lic           SOF           PLEASE REAL           This Software License Agree on which the Soft the date on which the Soft the Gate.") betwidentified on the Purchase           Image: Agree the terms in the lice on the soft of the terms in the terms in the lice on the soft of the terms in the terms in the terms in the lice on the soft of the terms in terms in the terms in ter	InstallShield Wizard cense agreement carefuly. TWARE LICENSE AGREEMENT D THIS DOCUMENT CAREFULLY greement ( <u>'Agreement</u> ) is effective as of the earlier of fiware is installed or the date of the Purchase Order veen Sargent & Greenleaf, Inc ( <u>'S&amp;G</u> ') and the party e Order ( <u>'Licensee</u> '). BACKGROUND Inste agreement the license agreement
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL This Software License Ag the date on which the So (the 'Effective Date') betw identified on the Purchase ○ I accept the terms in the lice ○ I go not accept the terms in InstallShield	InstallShield Wizard     Image: Constraint of the second sec
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL This Software License Ag the date on which the So (the 'Effective Date') betw identified on the Purchase I geoept the terms in the lice I go not accept the terms in the lice I go not accept the terms in the lice	InstallShield Wizard     Image: Constraint of the second sec
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL This Software License Ag the date on which the So (the 'Effective Date') betw identified on the Purchase	InstallShield Wizard     Image: Constraint of the second sec
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL This Software License Ag the date on which the So (the 'Effective Date') betw identified on the Purchase	InstallShield Wizard     Image: Constraint of the second sec
SG Audit Software - In License Agreement Please read the following lic SOF PLEASE REAL This Software License Ag the date on which the So (the 'Effective Date') betw identified on the Purchase ○ I accept the terms in the lice ○ I go not accept the terms in InstallShield	InstallShield Wizard       Image: Constraint of State St

🖨 Program Installation

SARGENT AND GREENLEAF\* STANLEY, STANLEY in a notched rectangle

\*

© 2011 Sargent and Greenleaf

System -

Type Software

SARGENT AND GREENLEAF and S&G, are trademarks of the Stanley Works or its affiliates

Sargent & Greenleaf, Inc.

SG Audit Software

Install .Net Version 4.0

Install Crystal Reports 13.0 Install Touchkey Drivers Install Program

# Installing the SG Audit Software (continued)

5. The customer information will be required next. Input the appropriate information and click the **Next** button to continue the installation.

6. Select the destination for the installation files and click the **Install** button to continue.

7. A summary of the installation information will be displayed. Click the **Install** button to begin the installation of the program files.

8. The installation status will be displayed on the screen during this routine.





🖟 SG Audit Software - InstallShield Wizard
Ready to Install the Program The wizard is ready to begin installation.
If you want to review or change any of your installation settings, click Back. Click Cancel to exit the wizard.
Current Settings:
Setup Type:
Destination Folder:
C:\Program Files\SG Audit Software\
User Information:
Name: Stanley Black Decker
Company: Stanley Black Decker
J InstallShield
< <u>B</u> ack Install Cancel



# Installing the SG Audit Software (continued)

9. Click the **Finish** button to complete the installation. The SG Audit Software should now be installed.



End of Software Installation Section

# Software Operation:

This section explains how your SG Audit Software works. It will let you perform the following operations:

- Clear a Touch Key's memory
- Format a Touch Key so that it can accept information from a lock
- Upload a new audit trail from a Touch Key
- View, print, and export an existing audit trail file
- Add, delete, or modify lock registrations
- Add, delete, or modify manager registrations

#### **Changing Logon Information**

1. When you start the SG Audit Software, you are greeted by the screen shown at the right.



2. To log on the first time you run the software, use "Administrator" for the **User ID** and "password" as the **Password**. User name and password entries are case sensitive.

Click **Ok** to bring up the main screen.



3. To insure the integrity of the audit trail system, you should change the **User ID** and **Password** immediately. You can also add additional managers at the same time.

From the View pull down menu, select Manager List.



When you click on the Modify button, you are presented with a screen that allows you to enter new User Name and Password information. When you have done this, click Save. You can click Close if you will not be adding any other managers at this time.

🚔 Manager List					3
User Name : Password :	Administrator		Cancel	Save	
Amana Amana	ger List				
	User Name : Password :	Ronald Smith		-	
				Cancel	Save
					Close

# **Adding and Deleting Managers**

- 1. From the **View** menu on the main screen, select **Manager List**. To add a manager, click **Add** and enter a **User Name** and **Password** for the new manager. Click **Save** followed by **Close** when the new entry is complete.
- 2. To delete an existing manager entry, click on the manager's **User Name** line in the **Manager List** to highlight it, then click **Delete**. Confirm the deletion when asked to do so. Note that it is not possible to delete all managers and leave the software without an administrator.

5G Audit Software	
ew Reports LogOut Help	
A Manager List	
User Name	Edit Manager Information
*	Add Delete
<u> </u>	Aanager List
	User Name : Ronald Smith
	Password :
	Cancel Save
	Close

# **Audit Upload Window**

## Lock Registration—Modify a Lock

From the **View** menu on the main screen, select **Upload Audit Trail**. You can click on any existing entry and **Modify** to change the information about any listed lock.

#### Lock Registration—Delete a Lock

You can click on any existing entry and **Delete** to completely remove an existing lock's information.

### Lock Registration—Add a Lock

You can create a new SG Audit Lock description by clicking the **Add** button.

### **About Lock Information Fields**

When modifying existing lock information or adding a new lock, here's what you need to know about each data field.

**Type of Lock:** You can select from **6126/6127** or **6128/6129**. This refers to the model number of your Sargent & Greenleaf lock. Subsequent data entry options are dependent on which set of lock models you select.

**Description**: Enter any description that will help you easily identify this particular lock and/or its location.

**Lock ID**: A unique serial number is provided on each lock body. Enter it here.

**Daylight Savings Enabled**: Check this box if the lock is located in an area that observes Daylight Savings Time. Otherwise, leave it unchecked.

**Programmer/Manager Code** (6126/6127 only): Enter the **Programmer Code** or **Manager Code** that is used to download the audit information from this particular lock (*see 6126/6127 lock operating instructions*).

**Using with Timelock Keypad** (6126/6127 only): If this lock is equipped with an optional Timelock Keypad, check this box. Otherwise, leave it unchecked. If you check this box <u>and</u> the Timelock Keypad is being used in encrypted mode, you <u>must</u> enter the 8-digit Timelock Keypad serial number. If you are using a Timelock Keypad but it is <u>not</u> in encrypted mode, you may enter eight zeroes in this box.

**PC Code** (6128/6129 only): Enter the 6-digit Programmer Code for this particular lock (see 6128/6129 lock operating instructions).

**Cipher Code** (6128/6129 only): Enter the 8-digit Cipher Code that is used to download the audit information from this particular lock (see 6128/6129 lock operating instructions).

#### When you have entered the necessary lock information, click Save.

ad		
FORMA	TION	
Descrip	tion	Lock ID
Downtow	wn Central Bar	k 40085647 Add
Franks C	Car Wash	CIEDEAAC Delete
Main Str	eet Gas Station	1 19334057 Modify
Prime Pi	zza	12340087
oload Key	/ Information	Request Report
R	ead Key	User PIN Position : ALL
	ave Data	
Fo	rmat Key	Keport
CI	lear Key	
	6	
	🖀 Audit U	pload
	Туре	e of Lock : 6126/6127
	Dese	sription : Main Street Gas Station
	Loc	x ID : 19334057
	_	
	V	Daylight Savings Enabled
	61	26/6127
		Programmer / Manager Code : 00123456
S		Using with Timelock Keypad
nck		🖨 Audit Upload
		Tura -61 -61/ (197
ify		
2		Description : Money Express
		Lock ID :  85705904
		✓ Daylight Savings Enabled
		6126/6127
. '		Programmer / Manager Code : 00123456
1		V Lising with Timelook Keynad
t		Keynad Savial Number : 12345678
		(only for Timelock keypad)
		Cancel
Ч		Class
u		LIOSE
		Audit Upload
		Type of Lock : 6128/6129 - 6128/6129
r		Description : North Super Center
		Lock ID : 75480185
		Cipher Code : 37850446
nis		I Vaylight Savings Enabled
-		
10		
/C.		Cancel
		Close

🖀 Audit Uple

тоски

# **Touch Key Preparation**

The Blue Dot Reader must be attached to a serial port or USB port of your computer to perform Touch Key operations.

From the **View** menu on the main screen, select **Upload Audit Trail** to view the **Upload Audit screen**.

Before a Touch Key can be used the first time, it must be formatted. Snap the key into the Blue Dot Reader. Click **Format Key**. The process takes approximately 30 seconds. Dialog boxes will ask you to confirm that you wish to format the key and notify you when the format is complete.



If desired, a Touch Key can be cleared (erased). Snap the key into the Blue Dot Reader. Click **Clear Key**. This action also takes approximately 30 seconds. A key does not have to be erased to be used for downloading an audit trail. If there is old information on the key, it will simply be overwritten by the new download. Dialog boxes will ask you to confirm that you wish to clear the key and notify you when the format is complete.

	Confirmation	
	Are you sure you want to clear	this key ?
Warning	×	No Yes
Clear Key (	Complete !	
	ок	

# Uploading and Saving the Audit Trail

Once an audit trail has been downloaded from a lock into the Touch Key, it can be read by the SG Audit Software. Remember that the codes in the lock's registration must match that used in the download of the audit trail from the lock.

Snap the key into the Blue Dot Reader. Click **Read Key**. If the upload cannot be accomplished, a dialog box appears to let you know that no usable data could be located on the key. Check the registered code information to make sure it matches what was used to download the audit trail from the lock. Try to read the audit trail again. If problems persist, use a different Touch Key, and check to make sure the time and date have been programmed into the lock.

When the upload is successful, the **Read Key Complete!** dialog box will appear. The upload process takes about 30 seconds.

If you are going to save the audit trail data, this is an excellent time to do it. Once the software has captured an audit trail, the **Save Data** button becomes usable. Click on it, and the audit trail information will be saved and cataloged by description, lock ID, time, and date. A dialog box will appear when the save operation is complete.

	ad	
LOCKI	NFORMATION	
	Description	Edit Lock Information
•	61505446	61505446 Add
	Audit Test Key #1	123456
	Audit Test Key #2	1234560 Delete
	Audit Test Key #3	12345600 Modify
	Audit Test Kev #4	12345700
	l	
arning	pload Key Information Read Key Save Data Format Key Clear Key	Request Report User PIN Position : ALL Report Close
Read Ke	ey Complete !	ОК
a <mark>rning</mark> Save Da	ta Complete !	

# Managing Audit Report Information

Select **View Previous Audit Uploads**, under the **Reports** menu found on the main page.

You can delete saved audit reports or change the descriptive information (**Description**, **Lock ID**, **Date/Time**) associated with the report by selecting the row containing the report you wish to delete or modify, then clicking on the appropriate button to the right of the reports list (**Delete** or **Modify**).

All saved reports can be viewed at any time by selecting the row containing the report you wish to view and clicking the **Report** button. You can select a particular PIN position (code holder) to view in the report, ignoring all others. If you leave the selector box set to **ALL**, all PIN positions (code holders) will be included in the report.

	-			Edit Papart Information
	Description	Lock ID	Date	Ear Neport mornation
•	61505446	61505446	9/22/2011 2:25:	D.L.
	Main Street Gas Station	19334057	1/27/2012 9:30:	Delete
*				Modify
				Request Report
				User PIN Position : ALL -
				,
				Кероп
_				

## Managing Audit Report Information (continued)

When you click on the **Report** button, the audit trail information will be displayed. The menus at the top of the window will let you view, manipulate, print, and save audit report information in a number of formats.

Audit trail information is displayed with the most recent activity at the top of the page, followed by the next most recent event, and so on. Each event is sequentially numbered and matched with a result, the time and date of the attempted action, and which user attempted the action. By knowing who the User Number was assigned to, you can identify the person performing the operation.

It should be noted that an entry stating "Bolt did not retract" could mean the battery was too low to open the lock, there was excessive side pressure on the bolt, or there was some mechanical issue preventing the lock bolt from retracting.

Any events captured by the lock prior to the time and date being set will have the date 1/1/00 assigned to them.



Sargent & Greenleaf Inc. Audit Report 1/27/2012

Date

Report Parameters : Main Street Gas Station Lock ID = 19334057 Daylight Savings Enabled Upload Date = 1/27/2012 9:30:27 AM User PIN Position = ALL

Event	Operation Description	Result	Operation Date / Time	Bank User
614	Download Command	Success	1/27/12 9:29 am	02
613	Comb. Added/Deleted	Success	12/12/11 11:38 am	03
612	Comb. Deleted - Authorizing Code	Success	12/12/11 11:38 am	09
611	Comb. Added/Deleted	Success	12/12/11 11:38 am	09
610	Comb. Added - Authonizing Code	Success	12/12/11 11:38 am	03
609	Comb. Added/Deleted	Success	12/12/11 11:37 am	03
608	Comb. Added - Authorizing Code	Success	12/12/11 11:38 am	02
607	Comb. Added/Deleted	Success	12/12/11 11:35 am	03
606	Comb. Deleted - Authorizing Code	Success	12/12/11 11:35 am	04
605	Comb. Added/Deleted	Success	12/12/11 11:35 am	04
604	Comb. Added - Authorizing Code	Success	12/12/11 11:35 am	03
603	Comb. Added/Deleted	Success	12/12/11 11:34 am	03
602	Comb. Added - Authorizing Code	Success	12/12/11 11:35 am	02
601	Lock Closed	Success	12/12/11 11:34 am	02
600	Lock Opened	Success	12/12/11 11:34 am	02
599	Download Command	Success	10/7/11 3:04 pm	00
598	Lock Closed	Success	10/7/11 3:01 pm	10
597	Lock Opened	Success	10/7/11 3:01 pm	10
596	Lock Closed	Success	10/7/11 3:01 pm	10
595	Lock Opened	Success	10/7/11 3:01 pm	10
594	Lock Closed	Success	10/7/11 3:00 pm	10
593	Lock Opened	Success	10/7/11 3:00 pm	10

#### **Software Version**

When checking for upgrades or speaking with a technical service representative about operating issues, you may find it helpful to know the software's version number. From the **Help** menu on the main page select **About**.